mosaic west coast



EQUIPMENT: YOU WILL NEED...

ESSENTIALS

- 30L fermenting vessel and lid with tap and airlock
- Large spoon
- Thermometer
- Detergent and sanitiser

OPTIONAL EXTRAS

- Hydrometer and iar
- Hop bag or hop ball
- 5 litre iug
- Heat pad, temperature controller, fridge



Н

Hot water for

5 minutes

Sterilising Solution





around gently for 30 seconds.



APPROXIMATE GRAVITY AND ARV

9

2L

Stir until dissolved

For a WEST COAST IPA we recommend you add:		19L	21L	23L
1.5kg Brick Road Light malt extract	OG	1.079	1.071	1.064
(OR Muntons Oat malt extract)	ABV	8.1%	7.2%	6.6%
PLUS 1kg Brick Road Light Dry malt extract	FG	1.016	1.014	1.013
(OR 1kg dextrose)				
For a LOWER STRENGTH WEST COAST IPA we recommend you add:				
1.5kg Brick Road Light malt extract	OG	1.056	1.051	1.046
	ABV	5.8%	5.2%	4.8%
	FG	1.011	1.010	1.009
For a SESSION IPA we recommend you add:				
1kg Brick Road Light Dry malt extract	OG	1.051	1.046	1.042
(OR 1kg dextrose)	ABV	5.3%	4.8%	4.3%
	FG	1.010	1.009	1.008


d) Mix. Open the cans and other fermentables and pour the contents into the sterilised fermenter, or into the 5L jug. Add 2L of boiling water and mix until smooth. Pour from the jug into the fermenter.

e) Top up with water. Top up with cold tap water to chosen volume. stirring well. Add any other ingredients like Drv Malt Extract. sugar and steeped hops. Option to take an original gravity (OG) reading.

Add rehydrated yeast

to the wort

1111 Top up with cool tap water



OTHER INGREDIENTS: OPTIONAL

Extra Hop Additions: For even more citrus or fruity aroma and flavour, add up to 200g of hops like Centennial, Cascade, Citra, Amarillo, Galaxy, Riwaka, Nelson Sauvin or Motueka, For more piney notes add Columbus or Tomohawk.

Alternate Yeast Options: US-05, Brv-97, WLP001 California Ale. 1056 American Ale or other clean, highly attentuating American ale veasts.

Water Treatment

MADE IN THE UK

Ideally, remove any chlorine from your water, Advanced brewers may wish to adjust water chemistry.

For more brewing information and recipes, visit www.brickroadbrewing.com



STAGE 2: DRY HOP

On Day 5 of fermentation add the 30g Mosaic hop pellets, and up to 100g of extra hop additions as desired. Ideally, put the hop pellets into a hop bag or hop ball, suspend them in the wort (use unscented dental floss), and remove after 48 hours.



Option: On Day 7 of fermentation add up to 100g of extra hop additions as desired.

HOPS

After about 10 days, the airlock should stop bubbling. Wait 3 more days to complete fermentation. Option to check gravity - if gravity

remains constant for 3 days. fermentation is complete. If in doubt, leave for a few more

davs. Once fermentation is complete. bottle or keg your beer. If bottling, clean and sanitise bottles. Use about 1 tsp sugar or two carbonation drops per 750ml bottle. Bottle condition for 3-4 weeks at room temperature. Sample your beer, and leave for longer if it still tastes like green apples (acetaldehyde). Pour gently as sediment will settle at the bottom.

Once your beer is tasting good. chill the remaining bottles. They will be good for 3-4 months, if For more brewing information and recipes, visit

more complex recipes.





BRICK

mosaic west coast IPA

Craft Beer Kit complete with AMERICAN ALE YEAST & MOSAIC DRY HOP PELLETS 30g

BREWING

TNSTRUCTTONS

ADDITIONAL FERMENTABLES REQUIRED

STAGE 3: BOTTLE OR KEG

they last that long!

www.brickroadbrewing.com

Tips: You will brew excellent beer following the basic instructions if you focus on three things: sanitation, temperature control and allowing time for fermentation and conditioning. We recommend you start with the simple recipe and once mastered move on to